# **NATUNLD Direct Command Syntax**

This section covers the following topics:

- General Information
- NATUNLD Syntax Diagrams
- Examples of Direct Commands for NATUNLD in Batch Mode

# **General Information**

After the execution of the direct command, you can enter another NATUNLD direct command, or END to leave NATUNLD, on the Input Command Data screen.

The individual items within each "with-...-clause" and "where-...-clause" can be specified in any sequence.

If you specify the parameter PC, specify it only once (as it applies to the entire work file); you have to specify it in the first possible "with-...-clause".

For error messages, the parameters FROM LIBRARY and TO LIBRARY are only valid for user-defined messages, not for Natural system messages.

The values following the keyword DIC in the "object-with-clause" and "ddm-with-clause" must be separated by commas. The commas must also be specified for omitted values.

For example: DIC (10,,SECRET,12)

If the session parameter ID has been set to comma, use slashes (/) instead of commas as separators.


For better readability, synonymous keywords are omitted from the syntax diagrams below. An underlined portion of a keyword represents an acceptable abbreviation.

Valid synonyms are:

Keyword	Synonym
DDM	<u>V</u> IEW
END	STOP
	QUIT
	FIN
FROM	FM
PASSWORD	PSW
UNLOAD	UNLD

# **NATUNLD Syntax Diagrams**


Copyright Software AG 2003



#### Below is information on:

- unload-objects-clause
- unload-ddms-clause
- unload-messages-clause
- object-where-clause
- object-with-clause
- ddm-where-clause
- ddm-with-clause
- message-with-clause
- delete-objects-clause
- delete-ddms-clause
- delete-messages-clause


# unload-objects-clause - for Programming Objects



### unload-ddms-clause - for DDMs

[ UNLOAD ] DDM ddm-name [ ddm-where-clause ]
[ ddm-with-clause ]

# unload-messages-clause - for Error Messages



# object-where-clause - for Programming Objects and Error Messages

```
[ WHERE ] [ DBID dbid ] [ FNR fnr ]

[ NAME vsam-name ] [ CIPHER cipher-key ] [ PASSWORD password ]
```

# object-with-clause - for Programming Objects

```
[ WITH ]

[ DIC ( dbid,fnr,password,cipher-key ) ]

[ FMDATE date ] [ TODATE date ] [ FMTIME time ] [ TOTIME time ]

[ SETNO set-number ] [ SETUSER set-user-id ] [NOSYMBOL-TABLE ]

[ TID terminal-id ] [TYPE object-types ] [USER-ID user-id ] [ XREF xref-setting ]

[ PC ] [ FIXEDLENGTH ]
```

#### ddm-where-clause

```
[ WHERE ] [ DDMDBID dbid ] [ DDMFNR fnr ]
```

#### ddm-with-clause

```
[ WITH ] [ DIC ( dbid.fnr,password,cipher-key ) ] [ PC ] [ FIXEDLENGTH ]
```

## message-with-clause

Copyright Software AG 2003 3

```
[ WITH ] [ LANGUAGE language-codes ] [ PC ] [ FIXEDLENGTH ]
```

# delete-objects-clause - Delete Instructions for Programming Objects

```
DELETE { ALL | SAVED | object-name FROM [LIBRARY] library-name [WITH] [PC]
```

#### delete-ddms-clause - Delete Instructions for DDMs

```
DELETE DDM ddm-name [ PC ]
```

# delete-messages-clause - Delete Instructions for Error Messages

```
DELETE ERROR { USER | SHORT | Start-error-number | [TOERR end-error-number] | [FROM [LIBRARY] library-name] | [message-with-clause]
```

# **Examples of Direct Commands for NATUNLD in Batch Mode**

In this example, all saved and/or cataloged programming objects of type program whose names start with PGM are unloaded from the library TESTLIB.

```
NATUNLD ALL PGM* FROM TESTLIB WITH TYPE P END
```

In this example, NATUNLD is placed in a separate line, and commas instead of blanks are used as separator characters. Apart from that, the example is identical to the previous one.

```
NATUNLD
ALL, PGM*, FROM, TESTLIB, WITH, TYPE, PEND
```

In this example, all programming objects saved on or after the 1st May 2000 are unloaded from the library OLDLIB, which is located on Database 100 in File Number 160. The objects are to be loaded into the library NEWLIB.

This example also shows the use of the continuation indicator (%) for a parameter string that is longer than a single line

```
NATUNLD
SAVED,*,FROM,OLDLIB,WHERE,DBID,100,FNR,160,%
FMDATE,00-05-01,TO,NEWLIB
END
```

In this example, all programming objects are unloaded from the library OLDLIB - together with their corresponding cross-reference data which are located on an FDIC file with File Number 20 on Database 10. The objects are to be loaded into the library NEWLIB.

```
NATUNLD
ALL,*,FROM,OLDLIB,DIC,(10/20//),TO,NEWLIB,%WITH,XREF,Y
END
```

This example shows the specification of multiple unloading instructions in one command.

#### NATUNLD

```
ALL, PROG1, FROM, TESTORD, DBID, 1, FNR, 6, PSW, PASSWD, TO, ORDERSMAIN CATALOGED, PGM*, FROM, TESTLIB, TO, PRODLIB, WITH, TYPE, PNS SAVED, PROG1, TO, NEWLIB END
```

Copyright Software AG 2003 5